
Christmas Trees | color chart

Each square is one US single crochet. Row 01 is the bottom row.



COLOR KEY

- A Pale icy-blue sky
- W Ivory snow
- D Deep forest tree
- O Olive tree
- L Light green tree
- T Brown trunks

READING THE CHART

Row 01 starts at the bottom. For a right-handed maker, work odd-numbered rows from the right edge of the chart to the left; even-numbered rows from left to right. Turn at the end of each row.

Small accents (berries, bows, ornaments, window details) are embroidered after the 28 crochet rows. The turquoise edging is added last and is not included in the 36 x 28 chart.

Christmas Trees | row-by-row pattern

Work 28 rows of 36 sc. Turn chains are not included in the stitch count.

BEFORE YOU BEGIN

Foundation: chain 37; single crochet in second chain from hook and across (36 sc). Chain 1 and turn at the end of every row. The turning chain does not count as a stitch.

Color changes: make the final yarn-over of the previous stitch in the next color. Use small bobbins to avoid long floats across the background.

COLORWORK ROWS 01-28

Example: 8W = make 8 consecutive sc in color W. The listed runs are already in working order.

01	RS ←	36W
02	WS →	36W
03	RS ←	36W
04	WS →	36W
05	RS ←	7W, 1T, 9W, 2T, 9W, 1T, 7W
06	WS →	7W, 1T, 9W, 2T, 9W, 1T, 7W
07	RS ←	1W, 1A, 11L, 12O, 9D, 1W, 1A
08	WS →	2A, 9D, 12O, 11L, 2A
09	RS ←	3A, 9L, 1A, 11O, 9D, 3A
10	WS →	3A, 9D, 11O, 1A, 9L, 3A
11	RS ←	4A, 7L, 2A, 11O, 1A, 7D, 4A
12	WS →	4A, 7D, 2A, 9O, 3A, 7L, 4A
13	RS ←	5A, 5L, 4A, 9O, 2A, 7D, 4A
14	WS →	5A, 5D, 3A, 9O, 4A, 5L, 5A
15	RS ←	5A, 5L, 5A, 7O, 4A, 5D, 5A
16	WS →	5A, 5D, 4A, 7O, 6A, 3L, 6A
17	RS ←	6A, 3L, 7A, 5O, 6A, 3D, 6A
18	WS →	6A, 3D, 6A, 5O, 8A, 1L, 7A
19	RS ←	7A, 1L, 8A, 5O, 7A, 1D, 7A
20	WS →	7A, 1D, 8A, 3O, 17A
21	RS ←	17A, 3O, 16A
22	WS →	16A, 3O, 17A
23	RS ←	18A, 1O, 17A
24	WS →	17A, 1O, 18A
25	RS ←	36A
26	WS →	36A
27	RS ←	36A
28	WS →	36A

Each row totals 36 sc. After Row 28, fasten off and weave in ends.

Christmas Trees | embroidery & finishing

Complete the crochet chart first, then add the smaller surface details.

MATERIALS & COLORS

- Smooth DK cotton or cotton-blend yarn in the chart colors (use the SAME yarn brand/weight for all three screens; quantities depend on measured gauge).
- 3.0-3.5 mm crochet hook as a starting suggestion only; adjust to your yarn and measured gauge.
- Blunt tapestry needle for weaving ends and embroidering motif details; scissors and stitch markers.
- Turquoise DK yarn for the optional matching one-round edging, worked the same on all three panels.
- Chart colors: A=Pale icy-blue sky, W=Ivory snow, D=Deep forest tree, O=Olive tree, L=Light green tree, T=Brown trunks.

FINISH THE PANEL

1. **Crochet a flat sky and snow background**

   Ch 37. Crochet Rows 01-28, 36 sc in each row, working from the bottom upward. The lower snow is ivory; the upper sky is pale blue.

2. **Work the three tree shapes**

   Follow the chart for three separate solid trees: dark forest green on left, olive in the center, light green at right. The brown trunks sit in snow. Work separate bobbins where colors are far apart.

3. **Protect the wrong side**

   At every color change make the last yarn-over with the incoming color. Do not drag yarn across wide blue spaces or wrap tight floats around the trees.

4. **Add baubles and stars**

   After rowwork, add a few embroidered yellow, red, pink and blue ornaments to each tree; gold star stitches can go at each tree tip. These accents are NOT part of the 36x28 color chart.

5. **Add subtle snowflakes**

   Use a few white yarn straight stitches in the sky, leaving enough calm negative space above the trees.

6. **Edge and flatten**

   Optional: add one turquoise sc border in the same method used on all three modules. Weave ends and block to the same final dimensions as the wreath and cottage.

SCREEN SIZING

All three panels use the same 36 x 28 stitch grid. Their finished physical size depends on your yarn, hook and gauge. Size the TV cabinet opening to the finished, edged panels, not to the older 20 x 14 TV sketch.