
Holiday Wreath | color chart

Each square is one US single crochet. Row 01 is the bottom row.



COLOR KEY

C Warm cream

G Deep evergreen wreath

READING THE CHART

Row 01 starts at the bottom. For a right-handed maker, work odd-numbered rows from the right edge of the chart to the left; even-numbered rows from left to right. Turn at the end of each row.

Small accents (berries, bows, ornaments, window details) are embroidered after the 28 crochet rows. The turquoise edging is added last and is not included in the 36 x 28 chart.

Holiday Wreath | row-by-row pattern

Work 28 rows of 36 sc. Turn chains are not included in the stitch count.

BEFORE YOU BEGIN

Foundation: chain 37; single crochet in second chain from hook and across (36 sc). Chain 1 and turn at the end of every row. The turning chain does not count as a stitch.

Color changes: make the final yarn-over of the previous stitch in the next color. Use small bobbins to avoid long floats across the background.

COLORWORK ROWS 01-28

Example: 8W = make 8 consecutive sc in color W. The listed runs are already in working order.

01	RS ←	36C
02	WS →	36C
03	RS ←	36C
04	WS →	36C
05	RS ←	36C
06	WS →	15C, 6G, 15C
07	RS ←	13C, 10G, 13C
08	WS →	12C, 12G, 12C
09	RS ←	10C, 16G, 10C
10	WS →	10C, 5G, 6C, 5G, 10C
11	RS ←	9C, 4G, 10C, 4G, 9C
12	WS →	9C, 4G, 10C, 4G, 9C
13	RS ←	8C, 4G, 12C, 4G, 8C
14	WS →	8C, 4G, 12C, 4G, 8C
15	RS ←	8C, 4G, 12C, 4G, 8C
16	WS →	8C, 4G, 12C, 4G, 8C
17	RS ←	8C, 4G, 12C, 4G, 8C
18	WS →	9C, 4G, 10C, 4G, 9C
19	RS ←	9C, 4G, 10C, 4G, 9C
20	WS →	10C, 5G, 6C, 5G, 10C
21	RS ←	10C, 16G, 10C
22	WS →	12C, 12G, 12C
23	RS ←	13C, 10G, 13C
24	WS →	15C, 6G, 15C
25	RS ←	36C
26	WS →	36C
27	RS ←	36C
28	WS →	36C

Each row totals 36 sc. After Row 28, fasten off and weave in ends.

Holiday Wreath | embroidery & finishing

Complete the crochet chart first, then add the smaller surface details.

MATERIALS & COLORS

- Smooth DK cotton or cotton-blend yarn in the chart colors (use the SAME yarn brand/weight for all three screens; quantities depend on measured gauge).
- 3.0-3.5 mm crochet hook as a starting suggestion only; adjust to your yarn and measured gauge.
- Blunt tapestry needle for weaving ends and embroidering motif details; scissors and stitch markers.
- Turquoise DK yarn for the optional matching one-round edging, worked the same on all three panels.
- Chart colors: C=Warm cream, G=Deep evergreen wreath.

FINISH THE PANEL

1 **Crochet the cream background and wreath ring**

Ch 37. Work 28 rows of 36 sc following Rows 01-28 on the color chart. The ring is tapestry colorwork in cream and green. Do not crochet red pixels; berry and bow details are sewn on afterwards.

2 **Change colors neatly**

Change cream/evergreen on the final yarn-over of the stitch before each color change. Use separate green bobbins for disconnected ring segments instead of dragging long floats across the cream center.

3 **Add red berries**

Use a tapestry needle to sew 10-12 small red dots around the green ring, anchoring each on the back.

4 **Embroider the bow**

At bottom-center of ring, stitch two red bow loops plus two tails with detached-chain/straight stitches. Do not sew a bulky bow that catches inside the future TV slot.

5 **Add matching turquoise trim**

Optional: work one loose sc border in turquoise, adjusting corner stitches to lie flat. All three screens must receive identical borders and be blocked to the SAME outer size.

6 **Finish as an independent screen**

Weave all ends into the wrong side. Block flat without stretching the picture. Measure width and height before sizing the separate TV cabinet.

SCREEN SIZING

All three panels use the same 36 x 28 stitch grid. Their finished physical size depends on your yarn, hook and gauge. Size the TV cabinet opening to the finished, edged panels, not to the older 20 x 14 TV sketch.