
Snowy Cottage | color chart

Each square is one US single crochet. Row 01 is the bottom row.



COLOR KEY

- A Pale icy-blue sky
- W Snow/white roof
- G Evergreen trees
- T Tree trunks
- B Oatmeal cabin facade
- D Dark walnut cottage wing and roof edge
- Y Warm window light

READING THE CHART

Row 01 starts at the bottom. For a right-handed maker, work odd-numbered rows from the right edge of the chart to the left; even-numbered rows from left to right. Turn at the end of each row.

Small accents (berries, bows, ornaments, window details) are embroidered after the 28 crochet rows. The turquoise edging is added last and is not included in the 36 x 28 chart.

Snowy Cottage | row-by-row pattern

Work 28 rows of 36 sc. Turn chains are not included in the stitch count.

BEFORE YOU BEGIN

Foundation: chain 37; single crochet in second chain from hook and across (36 sc). Chain 1 and turn at the end of every row. The turning chain does not count as a stitch.

Color changes: make the final yarn-over of the previous stitch in the next color. Use small bobbins to avoid long floats across the background.

COLORWORK ROWS 01-28

Example: 8W = make 8 consecutive sc in color W. The listed runs are already in working order.

01	RS ←	36W
02	WS →	36W
03	RS ←	36W
04	WS →	36W
05	RS ←	36W
06	WS →	36W
07	RS ←	2W, 2A, 1T, 2W, 3A, 2W, 3A, 8W, 2A, 2W 3A, 1W, 1T, 3A, 1W
08	WS →	4G, 1T, 4G, 1A, 6B, 2D, 4B, 7D, 2G, 1T 3G, 1A
09	RS ←	1A, 6G, 7D, 4B, 2D, 6B, 1A, 9G
10	WS →	1A, 7G, 2A, 6B, 2D, 4B, 7D, 5G, 2A
11	RS ←	2A, 5G, 2D, 4Y, 1D, 2B, 1D, 1Y, 2D, 1B 1D, 1Y, 1D, 2B, 2A, 7G, 1A
12	WS →	2A, 5G, 3A, 2B, 1D, 1Y, 1D, 2B, 1D, 1Y 1D, 2B, 1D, 4Y, 2D, 5G, 2A
13	RS ←	3A, 3G, 1A, 7D, 12B, 3A, 5G, 2A
14	WS →	3A, 3G, 3A, 20D, 1A, 3G, 3A
15	RS ←	4A, 1G, 1A, 21W, 3A, 3G, 3A
16	WS →	4A, 1G, 5A, 20W, 1A, 1G, 4A
17	RS ←	14A, 11W, 6A, 1G, 4A
18	WS →	12A, 9W, 15A
19	RS ←	10A, 2D, 4A, 7W, 13A
20	WS →	14A, 5W, 5A, 2D, 10A
21	RS ←	10A, 2D, 6A, 3W, 15A
22	WS →	16A, 1W, 7A, 2D, 10A
23	RS ←	9A, 4W, 23A
24	WS →	36A
25	RS ←	36A
26	WS →	36A
27	RS ←	36A
28	WS →	36A

Each row totals 36 sc. After Row 28, fasten off and weave in ends.

Snowy Cottage | embroidery & finishing

Complete the crochet chart first, then add the smaller surface details.

MATERIALS & COLORS

- Smooth DK cotton or cotton-blend yarn in the chart colors (use the SAME yarn brand/weight for all three screens; quantities depend on measured gauge).
- 3.0-3.5 mm crochet hook as a starting suggestion only; adjust to your yarn and measured gauge.
- Blunt tapestry needle for weaving ends and embroidering motif details; scissors and stitch markers.
- Turquoise DK yarn for the optional matching one-round edging, worked the same on all three panels.
- Chart colors: A=Pale icy-blue sky, W=Snow/white roof, G=Evergreen trees, T=Tree trunks, B=Oatmeal cabin facade, D=Dark walnut cottage wing and roof edge, Y=Warm window light.

FINISH THE PANEL

1. **Begin the snowy landscape**

   Ch 37. Use the 36x28 chart from Row 01 at the bottom; crochet exactly 36 sc per row and turn after each row with ch 1 (not a stitch). Start with the ivory snow field.

2. **Build the cottage and trees**

   Work brown trunks, evergreen side pines, oatmeal wall and dark cabin wing into the icy-blue sky. Change colors only at marked chart-cell boundaries; use small bobbins for separated areas.

3. **Work the snow-covered roof**

   Follow the chart for the WHITE gable and its lower extension; the brown chimney stands above the right section. This is a simplified crochet silhouette of the reference image, not a pixel-for-pixel replica.

4. **Define windows and a door**

   Follow the charted gold window blocks, then embroider fine window crossbars, door outline and roof edges with dark yarn. These extra outlines are surface stitches, so the 36-stitch row counts stay unchanged.

5. **Scatter snow and add a path**

   Add a few ivory straight-stitch snow marks against blue sky and a thin grey path at the cabin threshold. No additional rows are added.

6. **Finish and match all panels**

   Optional turquoise border; use the same edge method for all screens. Weave ends, block flat and take measurements before planning the TV pocket.

SCREEN SIZING

All three panels use the same 36 x 28 stitch grid. Their finished physical size depends on your yarn, hook and gauge. Size the TV cabinet opening to the finished, edged panels, not to the older 20 x 14 TV sketch.